



Imperial Stout

This full-bodied dark brew has an intense roast flavor with a huge malt influence. The hop bitterness is offset by a touch of sweetness from the big malt character. Give this beer some time to mature and consider using an oak alternative for added complexity.

IBUs: 58 - 62

OG: 1.085 - 1.089

FG: 1.023 - 1.027

ABV: 8.1% - 8.6%

Difficulty: Easy

Color: Black

Contents

- Ingredients
- Grain Bag
- Hops may vary due to availability.
- Priming Sugar
- Bottle Caps
- Brewing Procedures

Glossary

OG Original Gravity	DME Dried Malt Extract
SG Specific Gravity	LME Liquid Malt Extract
FG Final Gravity	IBU International Bittering Units (<i>Tinseth</i>)
CO₂ Carbon Dioxide	ABV Alcohol by Volume

Ingredients

FERMENTABLES
2 lbs. Amber DME
SPECIALTY GRAINS
4 oz. Black Barley
2 oz. Carapils
HOPS
12g Columbus Hops
7g Columbus Hops
YEAST
1 Sachet
(NOTE: you will only use 1 teaspoon of the provided yeast sachet.)

Recommended Procedures

BREW DAY (DATE ___ / ___ / ___)

1. READ

Read all of the recommended procedures before you begin.

2. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment and utensils that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

3. STEEP GRAINS

Pour 1.5 gallons of clean water into your brew pot and begin to heat. Pour crushed grains into grain bag and tie a loose knot at the top of the bag¹. When the water is within an appropriate steeping temperature (150° - 165°F) place the grain bag into the brew pot². Steep grains for approximately 20 minutes. Remove grain bag and without squeezing, allow liquid to drain back into brew pot. Your water is now wort.

4. START BOIL

Bring your wort to a gentle, rolling boil. Add **all of the included DME** to the boiling wort. Continuously stir the DME into the wort as it returns to a gentle, rolling boil³.

5. FOLLOW SCHEDULE⁴

As directed on the BREW DAY SCHEDULE (right), slowly sprinkle the first hop addition into the boiling wort (#1 in brew day schedule). Be careful not to let the wort boil over the pot. Using the provided BREW DAY SCHEDULE, note the time that each hop addition was added to the boil in order to keep your hop additions on schedule. Continue the gentle, rolling boil and follow the BREW DAY SCHEDULE until the boil is complete.

Recommended Brew Day Equipment

- 8 Quart or Larger Brew Pot
- 2 Gallon Pail w/Lid (primary fermenter)
- Screw Cap with Hole
- Airlock
- 1 Gallon Glass Jug (secondary fermenter)
- Hydrometer
- Thermometer
- No-Rinse Sanitizer
- Cleanser
- Spoon or Paddle

Brew Tips

¹The grains should not be compacted inside the bag. Grains should steep loosely allowing the hot water to soak into all of the grain evenly.

²Pay careful attention not to let your steeping water exceed 170°F which leeches tannins into the wort.

³Pay careful attention that the DME does not accumulate and caramelize on the bottom of your brew pot.

⁴When consumed, hops can cause malignant hyperthermia in dogs, sometimes with fatal results. Even small amounts, including "spent" hops from brewing, can trigger a deadly reaction.

BREW DAY SCHEDULE

1. Add 12 grams Columbus hops ___:___ (time)
2. Boil 40 minutes
3. Add 7 grams Columbus hops ___:___ (time)
4. Boil final 20 minutes
5. Terminate boil ___:___ (time)

Total Boil Time: 60 Minutes

Continue to Step #6



Recommended Procedures (continued)

6. COOL WORT & TRANSFER

Cool the wort down to approximately 70°F by placing the brew pot in a sink filled with ice water⁵. Siphon wort into a sanitized 2 gallon pail (primary fermenter)⁶. Avoid transferring the heavy sediment (trub) from the brew pot to the fermenter. Take an OG reading with a sanitized hydrometer and record it in your ABV% CALCULATOR (right).

7. PITCH YEAST

Measure out **1 teaspoon** of yeast (DO NOT REHYDRATE) and sprinkle the yeast over top of the entire wort surface and stir well with a sanitized spoon or paddle. Firmly secure the lid onto the fermenter. Fill your airlock halfway with water and gently twist the airlock into the grommated lid. Move fermenter to a dark, warm, temperature-stable area (approx. 64° - 72°F).

FERMENTATION

8. MONITOR & RECORD

The wort will begin to ferment within 24 hours and you will notice CO2 releasing (bubbling) out of the airlock. Within 4 - 6 days the bubbling will slow down and become intermittent or may stop completely. Once fermentation has slowed, rack your beer into your secondary fermenter (1 gallon glass jug). See **Two-Stage (Secondary) Fermentation** (right).

BOTTLING DAY (DATE ___/___/___)

9. READ

Read all of the recommended procedures before you begin.

10. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment, utensils, and bottles that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

11. PREPARE PRIMING SUGAR

In a small saucepan dissolve 1 oz. of priming sugar into 1/2 cup of boiling water for 5 minutes. Pour this mixture into a clean and sanitized 2 gallon pail. Carefully siphon beer from the secondary fermenter (1 gallon glass jug) into the 2 gallon pail. Avoid transferring any sediment. Stir gently for about a minute.

12. BOTTLE

Using your siphon setup and bottling wand, fill the bottles⁷ to within approximately one inch of the top of the bottle. Use a bottle capper to apply sanitized crown caps.

13. BOTTLE CONDITION

Move the bottles to a dark, warm, temperature-stable area (approx. 64° - 72°F). Over the next two weeks the bottles will naturally carbonate. Carbonation times vary depending on the temperature and beer style, so be patient if it takes a week or so longer.

**CHILL & ENJOY YOUR TASTY BREW AND THANK YOU FOR
CHOOSING BREWER'S BEST® PRODUCTS.**

Brew Tips

⁵To avoid bacteria growth do this as rapidly as possible. Do not add ice directly to the wort. Alternatively, you can use a brewing accessory like a Wort Chiller.

⁶If your 2 gallon pail doesn't have gallon markings, pour 1 gallon of water into the pail and mark the outside of the pail with a permanent marker for reference.

⁷Use standard crown bottles, preferably amber color. Make sure bottles are thoroughly clean. Use a bottle brush if necessary to remove stubborn deposits. Bottles should be sanitized prior to filling.

Two-Stage (Secondary) Fermentation

Brewer's Best® recommends home brewers employ the practice of a two-stage fermentation. This will allow your finished beer to have more clarity and an overall better, purer flavor. All you need is a 1 gallon glass jug, screw cap with a hole, airlock and siphon setup to transfer the beer. You will also need to monitor and record the SG with your hydrometer when the beer is in the 'primary'. When the fermentation slows (4-6 days), **but before it completes**, simply transfer the beer into the 1 gallon jug and allow fermentation to finish in the 'secondary'. Leave the beer for about two weeks and then proceed to Bottling Day. Consult your local retailer to learn more about this technique.

(SECONDARY RACK DATE ___/___/___)

Recommended Bottling Day Equipment

- 2 Gallon Bucket
- Siphon Setup
- Bottle Filling Wand
- 12 oz. Bottles (approx. 10)
- Brewer's Best® Crown Caps
- Bottle Brush
- Capper
- Sanitizer

ABV% Calculator

(OG - FG) x 131.25 = ABV%

(_____* - _____**) x 131.25 = ____%

*OG from Step #6

**FG from Step #8



Brewer's Best is a registered trademark of the LD Carlson Co.